



USER MANUAL

+32 (0) 2 533 04 80
support@logsize.com



Index

About Logsize

Web storage module

+32 (0) 2 533 04 80
support@logsize.com



About Logsize

Log stack volume measurement in record time

Save time

With Logsize log stack volume measurement becomes incredibly fast. You can measure up to 1000 logs in a few minutes.

Get precise results

Logsize measures log stacks in a consistent way thus reducing human errors in measurement.

Better data management

All your data is available online anytime and from any place. Multiple persons in the company can access the data and export it to the company's management systems.

About Logsize

How it works



Start Logsize app


Photograph log stack with
your device

The app determines the
volume and no. of logs

Data uploaded
to web storage module

Access the measurements on
your FMS or email

Storage module



The screenshot shows the LOGSIZE web login page. At the top is a red header with the LOGSIZE logo. Below it is a white login form with fields for Email and Password. A 'Forgot your password?' link is next to the password field. There is a 'Remember me' checkbox and a 'Sign in' button. At the bottom of the form are flags for the UK, France, Germany, and Spain. Below the form is a link for 'Didn't receive confirmation instructions?'.

LOGSIZE

Email

Password

[Forgot your password?](#)

☐ Remember me


[Sign in](#)

[Didn't receive confirmation instructions?](#)

Web address:
<http://app.logsize.com>

Login with the same credentials as on the
Android app.

Storage module



The screenshot displays the LOGSIZE web application interface. At the top, a red navigation bar contains the LOGSIZE logo, a 'Trial Upgrade' button, a 'Manage' dropdown menu, a 'Reports' icon, and a user profile 'fordaq' with a settings icon. Below the navigation bar, a green notification bar states 'Signed in successfully.' The main section is titled 'Measurements' and includes a 'Show Map view' link. The interface features several filter fields: 'Storage' (a dropdown menu), 'Measurement date' (two date input fields with a 'to' separator), 'Measurement type' (a dropdown menu), and 'Status' (a dropdown menu). Below these are 'Wood assortment' (a text input field), 'Length' (two input fields with a 'to' separator), and 'Volume' (two input fields with a 'to' separator). At the bottom of the filter section are 'Species' (a text input field) and 'Quality' (a text input field). A blue 'Filter' button is positioned below the 'Species' and 'Quality' fields. To the right of the 'Filter' button are two buttons: 'Save as Excel' (with a download icon) and 'Clear' (with an 'x' icon).

All the measurements done by your organisation's devices are stored in the storage module. Pictures can be viewed in table view (default) as well as map view. Users, devices, timber species and storages can be entered from Manage menu. Storages are synchronized with the device so all the information connected to storages and species will appear also in the device.

Storage module


Name	Coordinates	Last update	Status	Total
▼ fordaq	📍	2016-03-04	In progress	728.16 m³
Id / Measured on / Measurement type	Coordinates	Timber	Log length	Volume / Coefficient
March 2016				
Rezultat_2016-03-03_11-59-23 2016-03-03 Uncategorized		Brad	3.0 m	8.2 m³
Rezultat_2016-03-03_11-54-16 2016-03-03 Uncategorized		Brad	4.0 m	11.88 m³
Rezultat_2016-03-03_11-41-56 2016-03-03 Uncategorized		Brad	3.0 m	7.82 m³
Rezultat_2016-03-03_11-28-33 2016-03-03 Uncategorized		Brad	4.0 m	37.16 m³
Rezultat_2016-03-03_11-23-43 2016-03-03 Uncategorized		Brad	4.0 m	15.77 m³

Information can be filtered according to specific storage, date, measurement type or storage status. By clicking on the name of the storage, different measurements stored under this specific storage will open.

You can see a list of measurements with details for each one: specie, volume, measurement date, log length.

By clicking on one result, you will see the full detailed report with picture, diameters and volumes.

Storage module




Species: Quality:

[Filter](#) [Save as Excel](#) [Clear](#)

Name	Coordinates	Last update	Status	Total
▼ fordaq	📍	2016-03-04	In progress	728.16 m³
Id / Measurement type	Coordinates	Timber	Log length	Volume / Coefficient
March 2016				
Rezultat_2016-03-03_11-59-23 2016-03-03 Uncategorized		Brad	3.0 m	8.2 m³
Rezultat_2016-03-03_11-54-16 2016-03-03 Uncategorized		Brad	4.0 m	11.88 m³
Rezultat_2016-03-03_11-41-56 2016-03-03 Uncategorized		Brad	3.0 m	7.82 m³
Rezultat_2016-03-03_11-28-33 2016-03-03 Uncategorized		Brad	4.0 m	37.16 m³
Rezultat_2016-03-03_11-23-43 2016-03-03 Uncategorized		Brad	4.0 m	15.77 m³

You can see a list of measurements, with details for each one: specie, volume, when it was taken, log length

Storage module



Wood type: Brad

Wood quality:

Wood assortment:

Log length: 3.0 m

Volume formula: Cylinder

Reference size: 2.0 m

Volume: 18.0 m³ (Initial 18.12 m³)

Save or go back



By clicking on the picture, you will be able to see the determined logs and filter them by diameter.

Here you can also see the geo-localization and all the details that were entered in the android app.

Users with admin rights can modify data (for example, change the volume formula, wood quality or assortment).

Storage module



3 Log diameters

15 cm	1
24 cm	1
27 cm	3
29 cm	2
30 cm	4
31 cm	2
32 cm	3
33 cm	3
34 cm	1
35 cm	1
36 cm	3
38 cm	1
40 cm	2
41 cm	3
42 cm	1
43 cm	1
44 cm	2
45 cm	1
46 cm	3
47 cm	3
48 cm	3
49 cm	1
52 cm	1
53 cm	2
62 cm	1

Average 38.4 cm 49 in total

[Save as Excel](#)

By clicking on "Save as Excel", you will download the results in a file which can be imported in your own CMS system.

Storage module

The screenshot shows the 'Storages' module in the LOGSIZE application. The top navigation bar is red and contains the following elements: a logo, 'LOGSIZE', a 'Trial Upgrade' button, a 'Manage' dropdown menu, a 'Reports' button, and a user profile 'fordaq'. The 'Manage' dropdown menu is open, showing a list of options: 'Storages' (highlighted with a green box), 'Timber', 'Devices', and 'Users'. The main content area is titled 'Storages' and includes a search bar, a date range filter, and a table of storage records.

Search filters:

- Name:
- Created on: to
- Filter button
- Clear button

Storage records table:

Name	Coordinates	Status	Created on	
fordaq	,	In progress	2016-02-22	Delete

Manage -> Storages

This page displays a list of your organization's available storages, as well as the location, status and last updates on them.

To add a new storage click "Add" from top right. A view will be displayed, where the name of storage, location and status can be inserted.

Storage module

The screenshot shows the LOGSIZE web application interface. The top navigation bar is red and contains the LOGSIZE logo, a 'Trial Upgrade' button, a 'Manage' dropdown menu, and a 'Reports' button. The 'Manage' dropdown menu is open, showing options for 'Storages', 'Timber', 'Devices', and 'Users'. The 'Storages' option is highlighted with a green box. Below the navigation bar, the main content area is titled 'Storages'. It features a search bar with a 'Name' label, a 'Created on' date range selector, and a 'Filter' button. To the right of the search bar, there are two buttons: 'Add' and 'Add from CSV'. Below the search bar, there is a table with the following columns: Name, Coordinates, Status, and Created on. The table contains one row with the name 'fordaq', coordinates ',', status 'In progress', and created on date '2016-02-22'. A 'Delete' button is located to the right of the table row.


Name	Coordinates	Status	Created on
fordaq	,	In progress	2016-02-22

Manage -> Storages

You can also import storages from a CSV file.

For that select "Add from CSV" from top right. The CSV file needs to be in a correct format (name on every row, latitude, longitude).

Storage module



The screenshot shows the LOGSIZE application interface. At the top, there is a red navigation bar with the LOGSIZE logo, a 'Trial Upgrade' button, a 'Manage' dropdown menu, and a 'Reports' button. On the right side of the navigation bar, there is a 'fordaq' logo and a settings icon. A green arrow points from the 'Manage' dropdown menu to the 'Add wood type' button in the 'Wood types' table.

Wood types

Name	Archived
Pine	
Spruce	
Birch	
Aspen	
Alder	
Ash	
Oak	
Brad	no
Other	

[Add wood type](#)

Manage -> Timber


This page includes wood type, wood qualities, wood assortments and culls. All information is synchronized with the device, so all the options will also appear in the device.



Adding new wood types or wood qualities is taking place from top right, "Add wood type" or "Add wood quality".

Storage module

Manage -> Devices

This page displays all the devices connected to the account. You can add or unlink devices and see the number of measurements for each device.




Name	User email	Created on	Measurements	Last used at	Unlink
	it@fordaq.com	Mar 01, 2016	29	1 day ago	
	it@fordaq.com	Mar 01, 2016	0		



Logsize
[Terms & Conditions](#)

+32 (0) 2 533 04 80
support@logsize.com

Storage module



The screenshot shows the Logsize web interface. The top navigation bar is red and contains the Logsize logo, a 'Trial Upgrade' button, a 'Manage' dropdown menu, and a 'Reports' button. The user's name 'fordaq' is visible in the top right corner. The main content area is titled 'Devices' and features a table with two columns: 'Name' and 'User email'. The table contains two rows of data. Below the table, there is a footer section with the Logsize logo, a link to 'Terms & Conditions', and contact information: '+32 (0) 2 533 04 80' and 'support@logsize.com'. A green arrow points to the 'Add device' button located in the top right corner of the 'Devices' section.


Name	User email	Created on	Measurements	Last used at	Unlink
	it@fordaq.com	Mar 01, 2016	29	1 day ago	
	it@fordaq.com	Mar 01, 2016	0	never	

Manage -> Devices

Once you click on "Add device", there are 3 different options:

- Download Logsize through the link that is opened in the device;
- Send installing instructions to email;
- Install Logsize through Google Play and enter the company code displayed here.

Storage module



LOGSIZE Trial Upgrade Manage Reports

Users

+ Add user

Name	Sign in count	Last sign in at	Administrator
Admin	25	Mar 07, 2016	<input checked="" type="checkbox"/> yes Delete

Logsize
[Terms & Conditions](#)


+32 (0) 2 533 04 80
support@logsize.com

Manage -> Users

You can see a list of all the users linked to your organization.

In order to add a new user, click on top-right "Add user" button.

Storage module



The screenshot shows the LOGSIZE web application interface. At the top, there is a red navigation bar with the LOGSIZE logo, a 'Trial Upgrade' button, a 'Manage' dropdown menu, and a 'Reports' button. Below the navigation bar, the main content area is titled 'Users' with a user icon. On the right side of the 'Users' section, there is a green '+ Add user' button. Below this, there is a table with the following columns: Name, Sign in count, Last sign in at, and Administrator. The table contains one row for a user named 'Admin' with a sign-in count of 25, a last sign-in date of Mar 07, 2016, and a role of Administrator. There is a 'Delete' button next to the 'Admin' user entry. At the bottom of the page, there is a footer with the LOGSIZE logo, 'Terms & Conditions', and contact information: +32 (0) 2 533 04 80 and support@logsize.com.


Name	Sign in count	Last sign in at	Administrator
Admin	25	Mar 07, 2016	<input checked="" type="checkbox"/>

Manage -> Users

You can see a list of all the users linked to your organization. In order to add a new user, click on top-right "Add user" button.

To change the role of one user, click on the user's name and the detailed view on his data will appear. Users can be Administrators, Regular users or Measurers.

Storage module




The screenshot shows the LOGSIZE web interface. At the top, a red navigation bar contains the LOGSIZE logo, a 'Trial Upgrade' button, a 'Manage' dropdown menu (highlighted by a green arrow), and a 'Reports' button. The user's name 'fordaq' is visible in the top right. Below the navigation bar, the page title is 'Adding User'. The form contains the following fields: 'Name' (text input), 'Email' (text input), 'Password' (text input), 'Password confirmation' (text input), and 'Time zone' (dropdown menu set to '(GMT+02:00) Europe/Bucharest'). A blue 'Save' button is at the bottom of the form. The footer includes the LOGSIZE logo, 'Terms & Conditions', and contact information: '+32 (0) 2 533 04 80' and 'support@logsize.com'.

Manage -> Users

After clicking on "Add user", you will be prompted to add the name, email, password and timezone of the new user.

Storage module



The screenshot shows the LOGSIZE web application interface. At the top is a red navigation bar with the LOGSIZE logo, a 'Trial Upgrade' button, and links for 'Manage' and 'Reports'. A green arrow points from the 'Reports' link to a '+ New report' button in the top right corner of the main content area. Below the navigation bar, the 'Reports' section features a date range filter (with 'to' between two input fields), a blue 'Filter' button, and a 'Clear' link. A table displays two report entries:

Name	Volume formula	Volume unit	Date	Recipient organization	Confirmed
test	Cylinder	Metric	Feb 23, 2016		no
test	Cylinder	Metric	Mar 02, 2016		no


At the bottom left, there are links for 'Logsize' and 'Terms & Conditions'. At the bottom right, contact information is provided: '+32 (0) 2 533 04 80' and 'support@logsize.com'.

By clicking on Reports, you can see all the custom reports which you made.

You can make a new report by clicking on "New report" button.

For this, you have to create wood assortments prior to generating a report.

Storage module



The screenshot shows the LOGSIZE Reports page. At the top, there is a red navigation bar with the LOGSIZE logo, a 'Trial Upgrade' button, and links for 'Manage' and 'Reports'. A green arrow points to the 'New report' button in the top right corner of the page. Below the navigation bar, the 'Reports' section features a date range filter with 'Date' and 'to' input fields, a 'Filter' button, and a 'Clear' link. A table below the filter displays two reports, both named 'test', using the 'Cylinder' volume formula with 'Metric' units. The first report is dated 'Feb 23, 2016' and the second is dated 'Mar 02, 2016'. Both reports have a 'Confirmed' status of 'no'. At the bottom of the page, there is a footer with the LOGSIZE logo, 'Terms & Conditions' link, and contact information: '+32 (0) 2 533 04 80' and 'support@logsize.com'.


Name	Volume formula	Volume unit	Date	Recipient organization	Confirmed
test	Cylinder	Metric	Feb 23, 2016		no
test	Cylinder	Metric	Mar 02, 2016		no

Next step will be clicking on New report.

Enter the name of the report and select the formula that is used in calculating the volume.

You will have to add measurements to the report by clicking on "Add to report" in your dashboard.

Storage module



The screenshot shows the LOGSIZE web application interface. At the top is a red navigation bar with the LOGSIZE logo, a 'Trial Upgrade' button, and links for 'Manage' and 'Reports'. A green arrow points from the top of the page down to a '+ New report' button located in the top right corner of the main content area. Below this button is a 'Reports' section with a date range filter (two input boxes separated by 'to'), a blue 'Filter' button, and a 'Clear' link. Underneath the filter is a table with two rows of report data. The table has columns for Name, Volume formula, Volume unit, Date, Recipient organization, and Confirmed. The footer contains the LOGSIZE logo, 'Terms & Conditions' link, and contact information: '+32 (0) 2 533 04 80' and 'support@logsize.com'.

Name	Volume formula	Volume unit	Date	Recipient organization	Confirmed
test	Cylinder	Metric	Feb 23, 2016		no
test	Cylinder	Metric	Mar 02, 2016		no

After completing the steps, you can export your report to pdf or view them at any time.